


Temi Center User Guide

(Aug. 31, 2020)



Log in:

To log in to the temi Center go to - <https://center.robotemi.com/>.


You will need the latest version of the temi mobile app and for you temi to be on version 121 and above.

[For IOS Devices Click here](#)


[For Android devices Click Here](#)

On temi Center, click “Login”. A QR code will appear on the screen. On your mobile app, if using an Android device, go to the main menu and select “temi center login”. If you’re using an iOS device, go to “settings” and select “temi center login”. This will open a scanner on the mobile app to scan the QR code that appears on the screen. Point your phone to the QR code to initiate login.

Customize



Home Screen



Select what view of the Home Screen you would like to see.
Default – Admin call buttons and locations list will be shown.

Clear Screen – Screen will be completely empty from any widget.

Custom Screen – A customized screen with customized Function Buttons.

If you wish to customize your Home Screen, you can do so by selecting “Custom screen”, tapping the arrow on the right.

← Custom screen

Customize temi custom screen

Topbar

Immersive

Title

Insert your title here...

Tips

Add a tip here...

+ ADD TIP

Background image

Default

temi default wallpapers

Custom

Upload a pic of your own

Image optimal size 1280p x 800p

Topbar

Title

Tips

Function buttons

Background image

Top Bar – Select whether you would like the Top Bar to be hidden, shown or immersive.

Title – Provide a title that will appear on your home screen.

Tip – Add a lines of text.

Background image – Add a custom image that will appear in the background.

Function Buttons – Add your sequences to the Home Screen.

General Settings

These settings can also be configured on your temi.

Date and Time – You can select a 24-hour clock (the default is a 12-hour clock)

Battery – Select if you would like the battery percentage to appear on temi's screen and choose when temi will return to the Home Base to charge.

Standby – Activate power saving features when temi is idle

Touch Interaction – Configure the volume, power and interaction buttons

Voice Interaction – Enable/Disable if temi can be triggered by voice

Notifications – Configure navigation notification settings such as full screen or status label.

Navigation Settings

These settings can also be configured on your temi.

IMPORTANT: Please beware that adjusting temi's navigation settings can cause it to behave unexpectedly. It may fail to avoid obstacles, stairs and drops when not set up properly.

Obstacle Avoidance Profile – Let temi know if there are any stairs or drops in your home. IF YOU HAVE STAIRS OR DROPS IN YOUR ENVIRONMENT DO NOT SELECT "NO"

Obstacle Avoidance Sensitivity – Adjust temi's sensitivity to obstacles. Please note that selecting "Medium" might result in temi hitting objects while roaming.

"Go-to" Speed Control – Set the speed of temi's navigation to locations

Bypass Obstacles – Configure temi's behavior when facing an obstacle in its path


Navigation Timeout – Configure temi's timeout period when failing to navigate

Map

This will take you to the Map Editor (see further instructions below)

Control


To control your temi through the temi Center, tap "My temi" on the side menu. All the temis that you are the owner of and registered under your phone number will appear here.



Select the tēmi you wish to control and press the “Control” button. The most up to date map will appear on your screen, as well as the status of your robot. The tēmi icon on the map, represents its current location.




You can change the view of your map to see your locations, paths and virtual walls. Tap the “VIEW OPTIONS” on the right menu and select which items you would like to add to your view.



Use the “Scale” buttons to zoom in and out.

To send tēmi to an existing location, simply tap the desired location on your map. The tēmi icon will move accordingly to indicate the robot’s location as it makes its way to the location.

In addition, you can tap anywhere on your map and tēmi will go there, even without a saved location.



You can also access the Map Editor through the control screen, by selecting “Edit map”.

Editors:




Sequences

To access the Sequence editor, select Editors > Sequence on the side menu of temi Center.


Select “CREATE NEW SEQUENCE”

+ CREATE NEW SEQUENCE

Enter your Sequence name, picture and description, by tapping the edit button on the right

 **New Sequence** 

Edit New Sequence



Drag & Drop image here
or [Browse File](#)
(File size limit 200MB)

Name

Description

Discard

SAVE














To save your setting, click the “SAVE” button

Your Sequence editor is a matrix consisting of four actions that temi can perform, at a set order:

1. Movement - Go to location
2. Speak - Speak a written and vocal message

3. Media – Add an image you would like to display
4. Audio – Add a sound file you would like to play

STEPS

	 MOVEMENT	 SPEAK	 MEDIA	 AUDIO
STEP 1				
				

To create your sequence, on the matrix, press the + button at the center of the action you wish to add.

Each row represents a step in the Sequence. In each step, temi can perform all or some of the actions simultaneously.

You can choose to delay the start of each action inside each action's setting.

After configuring each action, hit "SAVE" to add the action to your Sequence.

Movement

Go to location

Filter by robot

Select Robot

Type in or choose the wanted location

Choose the delay for action to start

None

Discard

Save

Select which location you want temi to go to as part of your sequence.

Speak

Speak (Text to Speech)

Type what temi should say

input what temi should say



☐ Show text on temi screen

Available variables:

Person: First Name

Person: Last Name



Choose the delay for action to start

None

Discard


Save

Type in what you want temi to say. You can also have temi display the message on its screen.

Media

Upload Media

Choose which media temi should show



Drag & Drop image/video
here or [Browse File](#)
(File size limit 200MB)

Choose the delay for action to start

None ▾

Discard


Save

Upload an image or a video you wish to display as part of your sequence.
(recommended size for images is 1280X800 pixels for optimal resolution)

Audio

Upload audio

Choose which audio temi should play



Drag & Drop audio here
or [Browse File](#)
(File size limit 200MB)

Choose the delay for action to start

None ▾

Discard

Save


Upload an audio file for temi to play

Once you have finished the first step, you can add additional steps and actions.

Controlling and Activating your Sequence

Before playing your sequence, you can select which step you wish your sequence to start at and set the sequence to repeat.

To activate your sequence, go to the control bar at the bottom of the page. Select the robot you wish to activate the sequence on and press the Play button.




Map Editor

The Map Editor provides a convenient editing tool to make changes to your saved maps and increase *temi's* navigation capabilities. The Map Editor will allow you to add locations, “Paths” and “Virtual Walls”.

To access the Map Editor, select Editors > Map on the side menu of temi Center.

First, on the Map Editor page, select “Import map” to import a map from a specific temi to temi center, so you can start editing. Allow your map a few second to load, until it appears on the screen.

At any time you can select the map you want to edit out of your saved map. If you see saved maps you no longer need, you are welcome to delete them.



To begin editing your map, turn to Editor buttons at the bottom of the page.



Add a “Virtual Wall”

A “Virtual Wall” is an invisible barrier to block temi from getting into specific areas. We recommend you add Virtual Walls near staircases, steep drops, or glass walls.

To start, click the “Add Virtual Wall” button at the bottom of the page. Begin by marking a point on the map of where you would like the “Virtual wall” to begin. Continue marking points on the map until your Virtual Wall is created. When you’re finished, hit “Save” to save the changes.

Add Locations

To add a location, simply press on the point on the map where you want your location to be saved.

Please note that new locations can only be set inside an existing map. If you would like to set a location outside your map, please return to the robot’s map editor and use the “Continue Mapping” option.

Add Path

A Path will enable you to guide temi through the best and most efficient route from one destination to the other. Although temi is capable of navigating without it, a Path will ensure a smoother navigation experience.

To start, click the “Add Path” button at the bottom of the page. Begin by marking a point on the map of where you would like the path to begin. Continue marking points until you reach the desired destination. When you are finished, hit “Save” to save the changes.

Updating your Temi:

When you are finished editing your map, click “Send to Robot” at the bottom of the page. Select the robot you wish to update, and press “Send”. Your updated map will be sent to that *temi*.

Contacts:


Create or import contacts to your temi and create contact groups.


Create a new contact

To create a new contact, tap the “Add Contact” button and select “New contact”.

Create new contact

*Please fill in at least: First Name + Phone number or Email or Upload face recognition photo


Phone number  Enter a phone number

 First name* Enter a first name Last name Enter a last name

Gender Not Selected Email Enter Email

Description Input description

Face Recognition Photos


Drag & Drop image here
or [Browse File](#)
(maximum 5 pictures)
(File size limit 200MB)

Here will appear the
uploaded media

*Please make
sure the
contacts face is
showing clearly

Enter the information of your contact and press “Save” to add the contact

Import a mobile contact



To import an existing contact, tap the “ADD CONTACT” button and select “From Mobile App”. A list of your mobile phone contacts will appear on the screen. Select the ones you wish to add.


Copy contact from mobile group 0 Selected


Type contact name...


All contacts list Selected contacts


☐ Select All


 

 Amanda Muhammad

 Amir (Noa)

 Amy Gravesande

 Andrey Stepko

 Ani Baranov

After you have added the contacts, you will be able to edit it and add a picture, just like a new contact.

Groups

To create a group of contacts, select “Groups” from the side menu, and click the “Create Group” button. Name your group and hit “SAVE”

Create group

Group name

Discard

SAVE

After you opened your group, you can add contacts from either of your contact list or by creating a new contact.

